

USER GUIDE

Publishing Web UI

Release 9.3-MP3 (April 2020)

Table of Contents

Table of Contents	2
Publishing Web UI	4
Introduction	4
Print on Demand	5
Creating a new Print on Demand Publication	5
Set Publication Options	6
Manage Products	7
Review Publication	9
Review a saved Print on Demand Publication	10
Creating a New Print on Demand Publication based on an Existing Publication	10
Print on Demand Configuration Options	11
Email PDF to User	11
Show Review Publication Wizard Step	11
Show Template Previews	12
Actual Page Viewer	13
Page Revision Comparisons	15
Revision Compare Toolbar	15
Configuring Revision Compare Functionality on Actual Page	16
Configuring Actual Page Navigator	19
Working with Commercial Data in the Publishing Web UI	22
Configuring the Commercial Data Component in Web UI	22
Importing Commercial Data in Web UI	28
Importing the Commercial Data Spreadsheet	30
Editing Commercial Data in Web UI	30
Editing Terms	31

Limitations and Considerations	32
Additional Information	32

Publishing Web UI

Prior to STEP 8.2, users could choose between a number of Web UI templates when creating a Web UI. While these templates are now legacy functionality and not applicable to STEP 8.2+ systems, the information in the sample Web UI topics may benefit current users.

See the **Web User Interfaces** documentation for more information on Web UI functionality, which may not be reflected in this topic / section.

Note: Supported versions of Adobe InDesign are CC 2017 (CC12), CC 2018 (CC13), and CC 2019 (CC14).

Introduction

The purpose of a Publishing Web UI is to enable users to generate JPEG and PDF proofs of products and review publications. This can be done for an individual product (using the Proof View component) or for a selection of products to form a publication (using the Print on Demand component).

A Publishing Web UI also supports Publication Excel imports, side-by-side comparison of page revisions, and limited Flatplanner functionality.

The following are the main areas of functionality within a Publishing Web UI:

- Print on Demand
- Actual Page Viewer
- Planned Page Viewer
- Proof View
- Page Revision Comparisons
- Publication Excel import
- Commercial Data

Proof View is documented in the **STEP Publisher** documentation in the **Proof View** section.

Publication Excel imports are documented in the **STEP Publisher** documentation in the **Importing Publications in Excel** topic.

Print on Demand

To access the Print on Demand functionality, select the Print on Demand tab in the left hand side panel. You can create a new Print on Demand publication by selecting the '+' icon. Existing publications can be reviewed by selecting them in the Review Publications tree.

EN All All ▾ Main ▾ My Settings Logout

The screenshot displays the user interface of the STEP Publishing Portal. On the left, a sidebar titled 'Tree' contains several sections: 'Print on Demand' (highlighted in green), '+ Print on Demand Publication', 'Review Publications' (highlighted in green), and a 'Publications' folder icon. Below these are search and navigation fields for 'Search', 'Basket (4)', and 'Downloads'. The main content area on the right features a 'Welcome to the STEP Publishing Portal' message, followed by a brief description of the tool's purpose and a '+ Print on Demand Publication' button.

Creating a new Print on Demand Publication

Select the '+' icon. This will display the Print on Demand Wizard for creating a new Print on Demand Publication with the following steps available:

Set Publication Options

Tree

Print on Demand

+ Print on Demand Publication

Review Publications

Select an existing publication to review or edit the publication and generate a new PDF. Note: This tree has been configured to show the top level publication group but can be modified to show a sub-group instead.

> Publications

Search

Basket (4)

Downloads


1. Set Publication Options > 2. Manage Products > 3. Review Publication

Publication Name:


Start on Page:

Template:


Main Catalogue



Brochure



Flyer



Next

In this step of the wizard, you must specify a Publication Name for your new publication, specify a page number for the publication to start on and select a Template to base the publication on. A template can be selected by either using the template selection dropdown menu or by selecting from the template thumbnails. The template selection dropdown supports selection of the template by typing the first few letters of the template name.

Once a Publication Name and Template have been specified, the 'Next' button will become enabled. Pressing this will take you to the Next step of the wizard.

Manage Products

EN All All ▾ Main ▾ My Settings Logout

Tree

Print on Demand

+ Print on Demand Publication

Review Publications

Select an existing publication to review or edit the publication and generate a new PDF. Note: This tree has been configured to show the top level publication group but can be modified to show a sub-group instead.

> Publications

Search

Basket (4)

Downloads

1. Set Publication Options > 2. Manage Products > 3. Review Publication

Select All Clear Selection Add Items Remove Items Move Up Move Down


Thumbnail	Name	ID	Path
	Möbelhjul dubbellänkhjul typ KP	BBtool_BB5487	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ dubbellänkhjul typ KP
	Länkhjul typ AO 36	BBtool_BB5492	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ typ AO 36
	Plasthjul fasthjul typ FPR 86	BBtool_BB5470	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ fasthjul typ FPR 86
	Ottomanhjul typ FWR	BBtool_BB5457	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ typ FWR
	Plastlänkhjul typ FP 86	BBtool_BB5469	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ typ FP 86
	Möbelhjul bromshjul typ BKP	BBtool_BB5494	Primary Product Hierarchy/Custom Cases/BBTool PIMautopage/BBTools Arbetsplatsutrustning/Transp (BBtool_5448)/Transporthjul/ typ BKP

1-9 of 9

Back **Next**

In this step of the wizard, you can add or remove items from your publication and change the order in which they will be paginated.

Selecting 'Add Items' pops up a node chooser to allow you to browse or search for the Products, Assets or Classifications you wish to add to the publication. Multiple items can be added at the same time by using either Ctrl-Click or Shift-Click in the Browse tree.



Items can be removed from the list to be paginated by selecting item(s) from the item list and then selecting 'Remove Items.'

To change the order of the items in the pagination list, select the items you wish to move up or down the list and then select 'Move Up' or 'Move Down.'

Once items have been added to you publication, the 'Next' button will become enabled. Pressing this will take you to the next step of the wizard.

To go back to the previous stage of the wizard, press the 'Back' button.

Review Publication

Tree

- Print on Demand**
- Print on Demand Publication
- Review Publications**
- Select an existing publication to review or edit the publication and generate a new PDF. Note: This tree has been configured to show the top level publication group but can be modified to show a sub-group instead.
- Publications

Search

Basket (4)


Downloads

1. Set Publication Options > 2. Manage Products > 3. Review Publication


Publication Name: Documentation

PIM Autopage


4 / 1/3



4




5




6

INREDNING




Mobil hjul dubbelstremhjul typ KP
Med 2 stykker af en eller to hjul. Hjulet er monteret på en aluminiumsbænk.

Pris	Hjul diameter	Bænkens	Dyphøjde	Fladhedsradius	Fladheds diameter	Bj. i kg
5550202	25 mm	25 mm	25 mm	220 mm	2 mm	7 kg
5550204	27 mm	27 mm	27 mm	220 mm	2 mm	9 kg
5550203	25 mm	25 mm	25 mm	220 mm	2 mm	6 kg




Løsehjul typ AG 2H
Det gennemsnitlige hjulet består af en aluminiumsbænk og et hjul. Hjulet er monteret på en aluminiumsbænk. Hjulet er monteret på en aluminiumsbænk.

Pris	Hjul diameter	Bænkens	Dyphøjde	Fladhedsradius	Fladheds diameter	Bj. i kg
7704-0203	18 mm	18 mm	18 mm	18 mm	18 mm	4 kg
7779-0203	22 mm	22 mm	22 mm	18 mm	18 mm	20 kg
7779-0207	22 mm	22 mm	22 mm	18 mm	18 mm	4 kg
8206-0204	18 mm	18 mm	18 mm	18 mm	18 mm	4 kg
8206-0203	22 mm	22 mm	22 mm	18 mm	18 mm	20 kg
8206-0207	22 mm	22 mm	22 mm	18 mm	18 mm	4 kg



Fladstillet løsehjul typ FPE 5G
Med 2 stykker af en eller to hjul. Hjulet er monteret på en aluminiumsbænk. Hjulet er monteret på en aluminiumsbænk.

Pris	Hjul diameter	Bænkens	Dyphøjde	Fladhedsradius	Fladheds diameter	Bj. i kg
11610037	25 mm	22 mm	25 mm	40 mm	2 mm	21 kg
11610036	25 mm	22 mm	25 mm	40 mm	2 mm	21 kg



Dobbeltstremhjul typ I 4754
Med 2 stykker af en eller to hjul. Hjulet er monteret på en aluminiumsbænk. Hjulet er monteret på en aluminiumsbænk.

Pris	Hjul diameter	Bænkens	Dyphøjde	Fladhedsradius	Fladheds diameter	Bj. i kg
11610035	25 mm	18 mm	25 mm	40 mm	40 mm	19 kg
11610034	25 mm	18 mm	25 mm	40 mm	40 mm	19 kg
11610036	25 mm	18 mm	25 mm	40 mm	40 mm	19 kg
11610032	43 mm	15 mm	43 mm	40 mm	50 mm	23 kg

Back Get PDF Save & Finish Finish

In this step of the wizard you can review the publication, retrieve a PDF of the publication and save it.

To review a page of the publication, choose a version to review from the Version dropdown and then choose a page to review by either typing a page number into the page number field or using the left and right arrow page navigator icons or selecting the page thumbnail in the left hand column. A JPEG of the selected page is shown on the right hand side of the screen. This preview can be zoomed in and out by placing the cursor over the image and scrolling the mouse wheel.

To retrieve a PDF of the publication, select the 'Get PDF' button.

The publication can be saved by selecting the 'Save & Finish' button or can be discarded by selecting the 'Finish' button. Selecting 'Save & Finish' will display a tree browser from which the user can select where in the publication hierarchy to save the publication. Pressing either of the 'Save & Finish' or the 'Finish' button will take the user back to the portal home page.

To go back to the previous stage of the wizard, press the 'Back' button.

© Stibo Systems - Confidential - Release 9.3-MP3 (April 2020)

9

Review a saved Print on Demand Publication

EN All All ▾ Main ▾ My Settings Logout

Tree

Print on Demand

+ Print on Demand Publication

Review Publications

Select an existing publication to review or edit the publication and generate a new PDF. Note: This tree has been configured to show the top level publication group but can be modified to show a sub-group instead.


- Publications
 - Auto Test Publications
 - Customer Cases
 - Market Publishing Group
 - Module Mount
 - Print on Demand
 - PortalPublications
 - Documentation**
 - PortalPublicationTypes
 - PrintOnDemand_AutoTest
 - Slibo Area
 - Top Publication

1. Set Publication Options > 2. Manage Products > 3. Review Publication


Publication Name: Documentation

PIM Autopage


4 / 1/3



4




5




6

INREDNING




Möskjulig dubbelströmlig typ KP
Dubbelsladd med två stycken 100 mm breda och två stycken 100 mm breda hjul. Innehåller 100 mm breda hjul och 100 mm breda hjul.

Pris	Hjul diameter	Bredd	Djup	Flak diameter	Flak bredd	Stycktal
5550302	100 mm	100 mm	20 mm	100 mm	100 mm	2
5550304	100 mm	100 mm	20 mm	100 mm	100 mm	2
5550303	100 mm	100 mm	20 mm	100 mm	100 mm	2




Isarkjul typ AC 28
Dubbelsladd med två stycken 100 mm breda och två stycken 100 mm breda hjul. Innehåller 100 mm breda hjul och 100 mm breda hjul.

Pris	Hjul diameter	Bredd	Djup	Flak diameter	Flak bredd	Stycktal
7706-020	100 mm	100 mm	20 mm	100 mm	100 mm	2
7706-020	100 mm	100 mm	20 mm	100 mm	100 mm	2
7706-020	100 mm	100 mm	20 mm	100 mm	100 mm	2
8006-020	100 mm	100 mm	20 mm	100 mm	100 mm	2
8006-020	100 mm	100 mm	20 mm	100 mm	100 mm	2



Flaksladd Isarkjul typ FPE 50
Dubbelsladd med två stycken 100 mm breda och två stycken 100 mm breda hjul. Innehåller 100 mm breda hjul och 100 mm breda hjul.

Pris	Hjul diameter	Bredd	Djup	Flak diameter	Flak bredd	Stycktal
11610037	100 mm	100 mm	20 mm	100 mm	100 mm	2
11610036	100 mm	100 mm	20 mm	100 mm	100 mm	2



Dubbelsladd typ I 454
Dubbelsladd med två stycken 100 mm breda och två stycken 100 mm breda hjul. Innehåller 100 mm breda hjul och 100 mm breda hjul.

Pris	Hjul diameter	Bredd	Djup	Flak diameter	Flak bredd	Stycktal
11610035	100 mm	100 mm	20 mm	100 mm	100 mm	2
11610034	100 mm	100 mm	20 mm	100 mm	100 mm	2
11610033	100 mm	100 mm	20 mm	100 mm	100 mm	2
11610032	100 mm	100 mm	20 mm	100 mm	100 mm	2

Back
Get PDF
Save & Finish

From the Review Publications section of the Print on Demand tree, browse to the publication you wish to review and select it. This will display the publication in Step 3 (Review Publication) of the Print on Demand wizard.

Choose to 'Get PDF' for the publication which will retrieve a PDF of the publication or you can modify the publication by choosing the 'Back' button to take you to the previous steps of the wizard. The 'Save and Finish' will save any changes that have been made to the publication and take the user back to the portal home page.

Creating a New Print on Demand Publication based on an Existing Publication

Selecting an existing publication to review and then selecting the '+' icon to create a new Print on Demand Publication will pre-populate the item collection in Step 2 'Manage Products' of the Create New Publication wizard with the items that were in the originally selected existing publication. This allows the user to create a new publication based on an existing publication.

Print on Demand Configuration Options

The Print on Demand Web UI has various configuration options that are available in the Web UI designer. The key configuration options are listed. View the Print On Demand Web UI in design mode for further options.

The image displays two screenshots of the Web UI designer's Properties window, illustrating configuration options for the Print on Demand component and its associated NodeList component.

PrintOnDemand properties (Left Screenshot):

- Component Description:** A component for getting a PDF of a selection of products based on a Publication Type. Component is experimental and subject to change, use with care.
- Component status:** Component is experimental and subject to change, use with care.
- Configuration Options:**
 - BackButtonCssClass: [Empty]
 - BackButtonText: Back
 - EmailPDFMessage: PDF will be emailed to {0}
 - EmailPDFToUser:
 - FetchPDFProgressMessage: Fetching PDF ...
 - FinishButtonCssClass: [Empty]
 - FinishButtonText: Finish
 - ManageProductsStepLabel: 2. Manage Products
 - NextButtonCssClass: [Empty]
 - NextButtonText: Next
 - PDFButtonCssClass: [Empty]
 - PDFButtonText: Get PDF
 - PDFProfile: [Empty]
 - PaginationProgressMessage: Creating publication "{0}" using temp
 - PublicationNameLabel: Publication Name:
 - PublicationTemplateGroup*: PortalPublicationTypes
 - ReviewPublicationStepLabel: 3. Review Publication
 - SaveAndFinishButtonCssClass: [Empty]
 - SaveAndFinishButtonText: Save & Finish
 - SavePublicationRoot: [Empty] Clear
 - SetPublicationOptionsStepLabel: 1. Set Publication Options
 - StartPageDefaultValue: 1
 - StartPageLabel: Start on Page:
 - TempPublicationGroup*: PortalPublications
 - TemplateLabel: Template:
 - showReviewPublicationWizardStep:
 - showSaveOption:
 - showTemplatePreviews:
- Child components:**
 - NodeList: [NodeList] go to component

NodeList properties (Right Screenshot):

- Component Description:** Shows a list of nodes in one or several display modes. A detail panel can be added to the display modes for showing editors for the selection.
- Configuration Options:**
 - AssetSelectionScreen: <Select a screen> Add
 - ClassificationSelectionScreen: <Select a screen> Add
 - ClearSelection: Clear Selection
 - EmptySelectionScreen: <Select a screen> Add
 - EnableDefaultSorting:
 - EntitySelectionScreen: <Select a screen> Add
 - HideSelectionButtons:
 - ID *: PODNodeList
 - LookupScreenTypeForNavigation:
 - MultiSelectHelpText: [Empty]
 - MultiSelectionScreen: <Select a screen> Add
 - ObjectTypeScreenMapping: [Empty] Add... Edit... Remove Up Down
 - Page Size: 25
 - ProductSelectionScreen: <Select a screen> Add
 - SelectAllLabel: Select All
 - ToolbarHeight: 30
- Child components:**
 - DisplayModes:
 - TableDisplayMode
 - GalleryDisplayMode
 - FilmStripDisplayMode
Add... Remove Up Down
 - Actions:
 - AddPrintOnDemandItemsAction
 - RemovePrintOnDemandItemsAction
 - MoveItemsAction
 - MoveItemsAction
Add... Remove Up Down

Email PDF to User

If set, selecting 'Get PDF' will email the PDF to the user instead of returning it directly to the browser. The default setting is to return the PDF directly to the user.

Show Review Publication Wizard Step

This controls whether Step '3 Review Publication' is shown as part of the Print on Demand wizard.

Show Template Previews

This controls whether Template Previews are shown in Step '1 Set Publication Options' of the Print on Demand wizard.

Actual Page Viewer

To access the Actual Page View functionality, from the Tree on the left hand side, select a DTP document from within a publication.

EN All All Main My Settings Logout

Tree

- > Image Hierarchy
- > Primary Product Hierarchy
- > Publications
 - > Auto Test Publications
 - > Customer Cases
 - > Market Publishing Group
 - > Module Mount
 - > Print on Demand
 - > PortalPublications
 - > Documentation
 - > PIM Autopage
 - > Sub Section
 - > Möbelhjul dubbellänkhjul
 - > Länkhjul typ AO 36
 - > Plasthjul fasthjul typ FPF
 - > Ottomanhjul typ FWR
 - > Plastlänkhjul typ FP 86
 - > Möbelhjul dubbellänkhjul
 - > Möbelhjul bromshjul typ
 - > Hjul Lost Typ 36 Nylon
 - > Transporthjul
 - > 4-Sub-Section
 - > 6-Sub-Section
 - > PortalPublicationTypes
 - > PrintOnDemand_AutoTest
 - > Stibo Area
 - > Top Publication

DTP Document

PIM Autopage

4 / 12

There are no notes for this page

INREDNING

Orderelektion som ömslag

Möbelhjul dubbellänkhjul typ KP

2 dubbellänkhjul
Länkarna är för att stå. Det används i parker, traktorar
Kärl och tillhörande utrustning för
Bemannad bil och utrustning.

Pris	Hjul diameter	Bredd	Bygghöjd	Fästbultavstånd	Fästbult diameter	Storlek
1566005	25 mm	28 mm	29 mm	220,2 mm	2 mm	83 kg
1566004	28 mm	30 mm	32 mm	220,2 mm	2 mm	83 kg
1566002	28 mm	30 mm	32 mm	220,2 mm	2 mm	83 kg

Länkhjul typ AO 36

24 per meter och 40 styck per meter
Länkarna är för att stå. Det används i parker, traktorar
Kärl och tillhörande utrustning för
Bemannad bil och utrustning.

Pris	Hjul diameter	Bredd	Bygghöjd	Fästbultavstånd	Fästbult diameter	Storlek
7796 000	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg
7796 009	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg
7796 008	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg
828 019	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg
828 018	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg
828 087	12 mm	16 mm	16 mm	11 mm	11 mm	43 kg

Plasthjul fasthjul typ FPR 86

24 styck per meter och 40 styck per meter
Länkarna är för att stå. Det används i parker, traktorar
Kärl och tillhörande utrustning för
Bemannad bil och utrustning.

Pris	Hjul diameter	Bredd	Bygghöjd	Fästbultavstånd	Fästbult diameter	Storlek
11615077	20 mm	22 mm	22 mm	46 x 21 mm	6 mm	23 kg
11615058	20 mm	22 mm	22 mm	46 x 21 mm	6 mm	23 kg

Ottomanhjul typ FWR

Ottomanhjul typ FWR
Länkarna är för att stå. Det används i parker, traktorar
Kärl och tillhörande utrustning för
Bemannad bil och utrustning.

Pris	Hjul diameter	Bredd	Bygghöjd	Fästbultavstånd	Fästbult diameter	Storlek
11615015	25 mm	28 mm	28 mm	22 mm	2 mm	53 kg
11615024	25 mm	28 mm	28 mm	22 mm	2 mm	53 kg
11615033	25 mm	28 mm	28 mm	22 mm	2 mm	53 kg
11615032	25 mm	28 mm	28 mm	22 mm	2 mm	53 kg

4

4 styck per meter och 40 styck per meter
Länkarna är för att stå. Det används i parker, traktorar
Kärl och tillhörande utrustning för
Bemannad bil och utrustning.

Products | **Assets** | **Notes** | **Attribute**

ID	Name	Spaced Used
BBtool_BB5457	Ottomanhjul typ FWR	4805,16 mm ²
BBtool_BB5470	Plasthjul fasthjul typ FPR 86	3562,14 mm ²
BBtool_BB5487	Möbelhjul dubbellänkhjul typ KP	4136,69 mm ²
BBtool_BB5482	Länkhjul typ AO 36	7647,19 mm ²
BBtool_TT116130105	116130105	190,43 mm ²
BBtool_TT116130204	116130204	197,31 mm ²
BBtool_TT116130303	116130303	197,31 mm ²
BBtool_TT116130402	116130402	197,31 mm ²
BBtool_TT116150707	116150707	201,83 mm ²
BBtool_TT116150806	116150806	201,83 mm ²
BBtool_TT56540305	56540305	193,49 mm ²

To review an actual page of the publication, choose a version to review from the Version dropdown and then choose a page to review by either typing a page number into the page number field or using the left and right arrow page navigator icons or selecting the page thumbnail in the left hand column. A JPEG of the selected page is shown on the right hand side of the screen. This preview can be zoomed in and out by placing the cursor over the image and scrolling the mouse wheel.

Selecting the Products, Assets or Notes tab at the bottom of the screen will show more information about the content mounted on the actual page. From each of these tabs, selecting an entry in the table will highlight the selected content on the page.

Tree

- > Image Hierarchy
- > Primary Product Hierarchy
- > Publications
 - > Auto Test Publications
 - > Customer Cases
 - > Market Publishing Group
 - > Module Mount
 - > Print on Demand
 - > PortalPublications
 - > Documentation
 - > PIM Autopage
 - > Sub Section
 - > Möbelhjul dubbellänkhju
 - > Länkhjul typ AO 36
 - > Plasthjul festhjul typ FPR
 - > Ottomanhjul typ FWR
 - > Plastlänkhjul typ FP 86
 - > Möbelhjul dubbellänkhju
 - > Möbelhjul bromshjul typ
 - > Hjul Löst Typ 36 Nylon/
 - > Transporthjul
 - > 4-Sub Section
 - > 6-Sub Section
 - > PortalPublicationTypes
 - > PrintOnDemand_AutoTest
 - > Stibo Area
 - > Top Publication

DTP Document

PIM Autopage

4 1/2

4

5

There are no notes for this page

Products Assets Notes Attribute

ID	Name	Spaced Used
BBtool_BB5457	Ottomanhjul typ FWR	4885,16 mm ²
BBtool_BB5470	Plasthjul festhjul typ FPR 86	3592,14 mm ²
BBtool_BB5497	Möbelhjul dubbellänkhjul typ KP	4136,69 mm ²
BBtool_BB5492	Länkhjul typ AO 36	7647,19 mm ²
BBtool_TT116130105	116130105	190,43 mm ²
BBtool_TT116130204	116130204	197,31 mm ²
BBtool_TT116130303	116130303	197,31 mm ²
BBtool_TT116130402	116130402	197,31 mm ²
BBtool_TT116150707	116150707	201,83 mm ²
BBtool_TT116150806	116150806	201,83 mm ²
BBtool_TT56540305	56540305	193,49 mm ²


Note: It is also possible to review all actual pages within a publication or section. It require the Actual Page View functionality has been configured for these objects as well.

Page Revision Comparisons

The Publishing Web UI supports Revision Compare functionality for both actual pages and Flatplanner planned page spreads. This allows users to easily compare page revisions by highlighting where changes have occurred.

Revision Compare Toolbar

The 'Revision Compare' toolbar enables viewing of the latest page revision on the left half of the screen and a previous revision on the right. The previous revision to compare to can be selected from the 'Previous Revision' dropdown and differences can be highlighted by selecting the 'Show Differences' checkbox. This will result in the differences being highlighted on the latest revision while areas that have not changed are grayed out.



The system determines the differences between the two pages by looking at textual content changes and differences in space usage data. Text changes are highlighted whether the changes are made 'freehand' on mounted pages or if they originate from attribute value changes in STEP.

The Revision Compare functionality is available in the Publishing Web UI in the following components:

- Actual Page Revision Compare Proof
- Planned Spread Revision Compare Proof
- Planned Spread Revision Compare In Workflow

The Show Revision Toolbar option must be checked to enable the new functionality. If the box is not checked, the Revision Toolbar is not displayed and only the most recent page revision is visible.

For more information on Flatplanner planned page spreads and actual pages, see the **Overview of the Flatplanner User Interface** section of the **Flatplanner** documentation.

Configuring Revision Compare Functionality on Actual Page

Adding a New Actual Page Screen

To add a new Actual Page screen type, follow the steps below:

1. In the designer, click the **New** button in the action icon row.
2. Choose **Actual Page Screen** from the screen list and type in a Screen ID. The screen ID should be something


easily identifiable when it is time to configure the screen and/or set up screen mapping.

3. Click **Add**.

Configuring Actual Page Screen Properties

Once the screen has been added, follow the steps below to configure the Actual Page Screen Properties.

1. On the Actual Page Screen Properties go to Child Components > Main > Border Panel > click on **go to component**.



2. In the Border Panel Properties, go to Child Components > Main > Actual Page Revision Compare Proof > click on **go to component**.
3. On the **Actual Page Revision Compare Proof Properties**, there are a number of fields that can be filled out.

Properties

Configuration Web UI style

ActualPageViewer Save Close New... Delete Rename Save as...

Actual Page Revision Compare Proof [go to parent](#)
Properties

Component Description Displays the proof of an actual page and optionally compares it with a previous revision - selected via, say, the ActualPageNavigator

▼ Revision Toolbar

Current Revision Label	Current Revision:
Previous Revision Label	Previous Revision:
Show Differences Default Value	<input type="checkbox"/>
Show Differences Label	Show Differences
Show Revision Toolbar	<input checked="" type="checkbox"/>


Child Components

- **Current Revision Label:** This is the text that displays for the Current Revision Label on the Revision Toolbar.
 - **Previous Revision Label:** This is the text that displays for the Previous Revision Selector Label on the Revision Toolbar.
 - **Show Difference Default Value:** if this checkbox is selected, it will highlight the areas on the Current Revision where frame size / position or content differs from the selected Previous Revision. This is only applicable when the Show Revision Toolbar is set to True.
 - **Show Difference Label:** This text displays for the Show Difference checkbox on the Revision Toolbar.
 - **Show Revision Toolbar:** If set to true, the Revision toolbar will be shown. The Revision toolbar can be used to select a previous revision for comparing alongside the proof of the latest revision.
4. When finished configuration, click the Save button in the designer.

Configuring Actual Page Navigator

To configure the Actual Page Navigator, follow the directions below:

1. In the designer, click the New button.
2. Choose Node Details from the screen list, and type in a screen ID. The screen ID should be something easily identifiable when it is time to configure the screen and/or set up screen mapping.
3. Click Add.
4. In the node Details Properties go to Child Components > Main > Vertical Panel > go to component.



5. In the Vertical Panel Properties > Child Components > click Add > select the Row field and choose Actual Page Navigator > click Add.

Properties (edited)

Configuration Web UI style

Actual Page Navigat ▾ Save Close New... Delete Rename Save as

Vertical Panel Properties

[go to parent](#)

Component Description An Vertical Panel contain a list of components and arranges them vertical when displayed.

Css Class

Child Components

Rows

Add.. Remove Up Down

Add Component

Actual Page Navigator A component capable of navigating the actual DTP pages in a publication, section or document

Actual Page Overset

Aggregate

Approval Status

Asset Image Value

Asset Link

Asset Mid Sized


Asset Thumbnail

Filter

Show deprecated components

✓ Add ✕ Cancel

- In the Actual Page Navigator Properties for the Page Selection Screen field, select the Actual Page Screen created in the previous step.



- Select the Hide Navigation checkbox if the Navigation panel is not required.
- Click the Save button in the designer.
- Click Close the designer when finished.


Considerations and Limitations

- As of STEP 7.4, the Actual Page Revision Compare Proof, Planned Spread Revision Compare Proof, and Planned Spread Revision Compare In Workflow Web UI components automatically replace the previous Actual Page Proof, Planned Spread Proof, and Planned Spread In Workflow components.
- Planned pages must be mounted in InDesign and saved back to STEP before the Revision Compare functionality is enabled. Content changes to unmounted planned pages, e.g., replacing the content of a Flatplan frame, will not be highlighted as revisions.
- Users who have both a Flatplanner and Web UI license may compare revisions of mounted pages both from the Planned Spread Navigator and from the Actual Page Navigator in the Web UI. Users with a standard STEP Publisher (STEP'n'design) license can compare revisions of mounted pages from the Actual Page Navigator only.
- Though the Revision Compare feature highlights changes in textual content, this feature is primarily designed to highlight differences in space usage between the two revisions. It does not highlight changes in images, frame colors, paragraph styles, or layouts if the space usage remains the same.

Working with Commercial Data in the Publishing Web UI

Commercial data (commercial terms lists) may be imported, viewed, and edited in the Publishing Web UI.

This is accomplished by adding the **Commercial Terms Editor** component to the Node Editor for publication objects. Available as a Node Editor child component, the Commercial Terms Editor is intended to use only on Node Editor configurations used to work with publication objects.




Visible term fields for commercial data lists in the Web UI are the same as those in the workbench: Value, Unit, Min Quantity, Max Quantity, Start Date, and End Date.

The following sections of this topic explain how to configure, import, and edit commercial data terms lists in the Publishing Web UI.


Configuring the Commercial Data Component in Web UI

Follow these steps to configure the commercial data terms lists component in the Publishing Web UI:


1. In your Publishing Web UI, navigate to a publication object in the publication hierarchy.
2. With the publication object selected, enter design mode.
3. In the dropdown list that appears in the upper left corner of the Web UI Designer, the screen ID for the Node Details screen created for publication objects should already be selected. In this example, this screen is named **publicationdetails**.




4. In Child Components > Main, make sure that **Tab Control** is selected. Click 'go to component.' The Tab Control component appears in the designer.
5. Under Child Components > Tab Pages, click **Add**.



6. In the **Add component** dialog that displays, select **Tab Page**, then click **Add**.



7. Double click on the newly created tab page in the Tab Pages list. **Tab Page Properties** displays.
8. In the Title field, add a descriptive title that should appear on the new tab (for example, Commercial Data). Select **Vertical Panel** as the Tab Content child component.



9. Click 'go to component' to display **Vertical Panel Properties**.
10. In Child Components > Rows, click **Add**.
11. In the **Add component** dialog, select **Commercial Terms Editor**, then click **Add**.



12. Double click the **Commercial Terms Editor** component to open **Commercial Terms Editor Properties**.

Properties - Configuration Saved!

Configuration **Web UI style**

publicationdetails Save Close New... Delete Rename Save as...

Commercial Terms Editor Properties [go to parent](#)

Component Description A screen for viewing and editing Commercial Terms Lists for a Publication

Commercial List Object Types

Add... Remove Up Down

Valid Units

Add... Remove Up Down

Show Unit Header

Show Min Quantity Header


Show Max Quantity Header

Show Start Date Header



Show End Date Header

Child Components

13. Click the **Add** button in the **Commercial List Object Types** section. The **Select Node(s)** dialog displays.
14. Select the commercial data object type(s) that should be valid in the commercial terms editor. Multiple commercial types may be selected at once by pressing Ctrl or Shift while making selections. Click **OK** when finished.



15. Click the **Add** button in the **Valid Units** section. The **Select Node(s)** dialog displays.
16. Select the unit(s) that should be valid in the commercial terms editor. Multiple units may be selected at once by pressing Ctrl or Shift while making selections. Click **OK** when finished. (Units used in commercial data are typically currency units.)



17. Check the relevant boxes beneath the Valid Units area to configure which headers should display in the commercial data table on the Commercial Terms Editor screen.

ID	Value	Unit	Min Quantity	Max Quantity	Start Date	End Date
----	-------	------	--------------	--------------	------------	----------

18. Click the **Save** and **Close** buttons at the top of the designer to save your configurations and close the designer.

Importing Commercial Data in Web UI

Commercial data may be imported in the Web UI by using Excel spreadsheets containing the commercial terms information for products in the selected publication.


Note: Before commercial data can be imported into a publication in the Web UI, at least one import configuration for commercial data must have already been created on the publication in the workbench. See the **Defining Import Settings for Commercial Data** section of the **Commercial Data** documentation for information on how to configure import configurations for commercial data in the workbench.

The import process is accomplished by using the **Import Commercial Terms** button on the **Publication Node Editor** screen.


Import Commercial Terms

To add this button to your screen, follow these steps:

1. Navigate to **Node Details Properties** in the designer by following steps 1 - 3 in the previous section of this topic.
2. In the **Child Components** section, select **Buttons** in the Buttons dropdown list, then click 'go to component.'



3. The **Buttons Properties** component displays in the designer. In the **Child Components** area, click the **Add** button. In the **Add component** dialog that displays, select **Import Commercial Terms** from the dropdown list. Click **Add** to close the dialog.



4. Click the **Save** and **Close** buttons at the top of the designer to save your configurations and exit design mode.
5. The **Import Commercial Terms** button is now added at the bottom of the screen.

Note: The Import Commercial Terms button is not activated unless you have selected a publication in the Tree area that has at least one import configuration already defined in the workbench.

Importing the Commercial Data Spreadsheet

Follow these steps to import a spreadsheet containing your commercial terms information:

1. In the Tree area, navigate to the publication into which you would like to import your commercial terms spreadsheet, then navigate to the Commercial Data tab on the **Publication Node Editor** screen.
2. Click the **Import Commercial Terms** button. The **Import Commercial Terms** dialog displays.

3. If the publication has multiple import configurations, select the relevant configuration from the **Import Configuration** dropdown list.
4. Click the **Choose File** button to select the spreadsheet that you would like to import.
5. Select 'Replace entire existing list(s) with content of import file' to remove all contents of the existing list and replace those terms with the contents of the new sheet. Select 'Only update commercial data for objects included in import file' to add new terms and overwrite existing terms for products already on the list.
6. Click **OK** to close the dialog. A background process begins for the commercial terms list import.
7. When the background process successfully completes, the commercial terms are added to the commercial list.

Editing Commercial Data in Web UI

Once commercial terms have been imported into the commercial data list(s) connected to your publication, both the terms values and configurations of the lists themselves can be edited in the Web UI.

To edit configurations for commercial terms lists in the Web UI, follow these steps:

1. In the Tree area, navigate to the publication that contains the commercial terms that you would like to edit.
2. Navigate to the Commercial Data tab on the **Publication Node Editor** screen, then select the relevant commercial data terms list from the **Select Commercial List** dropdown. The **ID** and the **Object Type** of the list will automatically display.

Publication

Publications > Standard Publications > Acme Tools

Details Proof Plan Print On Demand **Commercial Data**

Select Commercial List: Acme Tools Spring Pricing

ID: AcmeToolsSpringPricing

Object Type: Price

Default Unit:

Default Start Date:

Default End Date:

Expiry Date:

Immutable:

3. In the **Default Unit** field, choose the default unit from the dropdown list. (This list is populated by the valid units that were selected when the **Commercial Terms Editor Properties** screen in the Web UI designer was configured.)
4. For **Default Start Date**, **Default End Date**, and **Expiry Date**, either click in the field and select a date from the popup date picker or manually enter a date that matches the 'ISO Date and Time' format of **yyyy-MM-dd HH:mm:ss**.
5. Check the **Immutable** box to make the values of the terms list uneditable by any user.

Editing Terms

To edit the values of terms lists, follow these steps:

1. Click the node picker button to the right of the **Product** (product search) field to locate a product in your commercial list.

Product: 

ID	Value	Unit	Min

2. In the **Select Product** dialog that displays, either browse to or search for the relevant product, then click **OK**. Note that only one product at a time may be selected.
3. The product displays in the commercial data table.


Product: Torque wrench (42304)

ID	Value	Unit	Min Quantity	Max Quantity	Start Date	End Date
Torque wrench	42304	101.99	1	3		

4. Contents of the **Value**, **Min Quantity**, and **Max Quantity** fields are typed. The value for **Unit** is chosen from a dropdown list (which contains the valid units that were selected when the **Commercial Terms Editor Properties** screen in the Web UI designer was configured).

The values for **Start Date** and **End Date** can be typed or chosen from a date picker. To view a sample of the required ISO format for the date field(s), select the field and double click. To access the date picker, select the field and triple click.


- To add an additional term for the product, click the add terms icon. An additional term may be needed, for example, to add an additional price for a price break.



Product: Torque wrench (42304)

	ID	Value	Unit	Min Quantity	Max Quantity
Torque wrench	42304	101.99	\$ (iso4217.unit.USD)	1	3
Torque wrench	42304	89.99	\$ (iso4217.unit.USD)	4	11

- To remove terms, select the row(s) containing the unwanted term(s), then click the remove terms icon. Rows may be multi-selected either by pressing Ctrl or Shift while making selections or by checking the 'select all' icon in the upper left (to the left of the product search field).



Product: Torque wrench (42304)

	ID	Value	Unit	
Torque wrench	42304	101.99	\$ (iso4217.unit.USD)	1
Torque wrench	42304	89.99	\$ (iso4217.unit.USD)	4

- Click the **Save** button at the bottom of the screen to save all changes. Automatic saving while performing edits of commercial terms is not possible in the Web UI.

Limitations and Considerations

- Terms may be viewed and edited for only one product at a time in the Web UI.
- The toolbar is not configurable. Select / deselect all, product search, and add / remove terms are always shown.

Additional Information

For information on how to configure import configurations for commercial data in the workbench, see the **Defining Import Settings for Commercial Data** section of the **Commercial Data** documentation.

For general information on commercial data in STEP, see the **Commercial Data** section of the **STEP Publisher (InDesign)** documentation.